

Shorts "Romy"

Model 222-28

Size 36-48



PRINT THE CUT

1. Open the pattern PDF and set the control square to Page 1 with the setting "Original size" on DIN Print A4 paper (US-Letter). (Do not click on "Adjustment to page size"!)
2. Check the square – if it is 10×10 cm, print out the whole cut sheet.
3. Place all pages next to each other as indicated by the arrows and adhere them row by row along the boundary lines, then glue the rows together.
4. Compare the body measurements with the table measurements and cut out the cut parts in the appropriate size. (The overview of the cut parts is on the pattern sheet.)

Important: Instructions do not include seam allowances, unless otherwise indicated!

SUPPLIES

- 0.7–0.9 m rayon jersey, 150 cm wide
- Woven interlining G 785 (Vlieseline)
- 0.7–1.0 m elastic, 2 cm wide

OPTIONAL BERNINA ACCESSORIES

- Overlocker
- [Binder Attachment for Unfolded Bias Tape #88](#)
- [Binder Foot #95](#)

CUTTING

- 1 2× front part
- 2 1× hip yoke on the fold
- 3 2× pocket bag
- 4 2× back part
- 5 1× waistband on the fold

Edging strip: 130 up to 160×4 cm, final width 1 cm.

INSTRUCTIONS

1. Iron Vlieseline on the pocket mouths and let them cool off thoroughly. Sew the pocket bags right side on right side along the pocket mouths. Place the allowances towards the pocket bags and narrow-topstitch them. Turn the pocket bags inwards and fix them. Close the centre seam of the front parts. Pin the hip yoke with the markings under the pocket mouths and the front part. Close the pocket bags and sew the upper edges together on the allowance.
2. Close the side seams and the bottom seam. Close the waistband right side on right side to form a ring, leaving an opening for the elastic on the inner side of the waistband. Fold the waistband lengthwise wrong side on wrong side and iron it on the folded edge. Sew the waistband right side on right side along the upper edge of the trousers. Insert the elastic and sew the ends together. Topstitch the waistband vertically over the elastic at both sides and in the rear centre or, alternatively, all around the waistband in the centre of the elastic.
3. Fit the Binder Attachment and the Binder Foot and bind the hems of the trousers. As an alternative, sew the edging tapes right side on right side on the hems of the trousers. Fold the loose edge inwards, fold it in and pin it in place. Topstitch it from the right. Close the inner leg seams.

