SEWING INSTRUCTION

Blouse "Eva"
Model 7212
Sizes 36 – 48

PRINT THE CUT

1. Open the pattern PDF and set the control square to Page 1 with the setting "Original size" on DIN Print A4 paper (do not click on "Adjustment to page size"!)
2. Check the square – if it is 10 x 10 cm, print out the whole cut sheet.
3. Put all pages together as shown in the overview and attach them to the boundary lines row by row. Then glue the rows together.
4. Compare the body measurements with the table measurements and cut out the cut parts in the appropriate size (the overview of the cut parts is on the pattern sheet). **Important:** Instructions do not include seam allowances, unless otherwise indicated.

SUPPLIES

- 1.4 – 1.8 m rayon fabric, 135 cm wide
- Remnant of cotton fabric, in Bordeaux
- Vlieseline H 180
- 0.4 – 0.5 m elastic, 7 mm wide
- 7 buttons, 12 mm in diameter (Union Knopf)
- Woollen yarn in 3 different colours
- Water-soluble stabiliser "Soluvlies" (Vlieseline)
- Embroidery accessory
- Free embroidery file; refer to Inspiration 72
- BERNINA embroidery machine
- Mega Hoop
- Cording foot 43
- Button sew-on foot 18

CUTTING

1 × front on the fold
2 × back
1 × facing for the neckline on the fold
2 × upper sleeve
2 × lower sleeve

Strip of piping 60 – 80 × 3 cm, final width 0.4 cm.

SEWING INSTRUCTION

Blouse "Eva"
Model 7212
Sizes 36 - 48

INSTRUCTIONS

1. Iron the Vlieseline on the facing of the neckline, the back of the cut button facing and the position of the relief embroidery (centre of the embroidery about 12 cm above the hem of the sleeve edge) if necessary. Let it cool off thoroughly.

2. Hoop the water-soluble stabiliser in the hoop; place the embroidery. Tip: With the new function "Pinpoint placement", you can do this without a template. Fix the stabiliser on the fabric with the function "Basting the outline of the motif". Insert woollen yarn, which is not too elastic, into the foot 43 and attach the foot. Reduce the speed and make sure that the yarn can be embroidered in an unimpeded way. After embroidering, pull the yarn ends to the back and tie. Wash out the stabiliser.

3. Close the darts, shoulder and side seams. Iron the button facing to the inside twice along the marked lines. Fold it to the outside along the line "Break", pin the upper edge. Sew the facing right side on right side on the neckline, then sew the upper edge of the button facing. Clip the allowances in the curves. Fold the facing and the button facing to the inside. Sew and turn the button facing at the hem, topstitch the hem and the button facing without interrupting. Fix the facing on the shoulder seam.

4. Iron the piping on the fold and sew it right side on right side on the lower edges of the upper sleeves. Gather the upper edge of the lower sleeve so that it matches with the width of the lower edge of the upper sleeve. Fold the seam allowance to the inside of the upper sleeve and topstitch with the Edgestitch foot. Close the sleeve seams. Gather the top shaping and sew the sleeves into the armholes. Hem the sleeves, leaving about 1 cm open for the elastic. Topstitch the fold with the Edgestitch foot, insert the elastic and sew the ends together.

5. Sew button holes at the distance of about 8.5 cm in the right back part. Attach the Button sew-on foot and sew on the buttons on the left back part.