

BERNINA 530/550 - Firmware Update

Note

The following step-by-step instructions will show you how to install the BERNINA maintenance software on computers with one of these operating systems: Windows® XP, Windows Vista™ or Windows® 7.

The actual file names and illustrations might differ from the ones shown depending on the operating system and internet browser installed on the pc.

The illustrations used in the instructions refer to Windows® 7 and Internet Explorer 9.

System requirements for the installation of the software:


- Operating system: Windows® 7 (SP1), Windows Vista™ SP2, Windows® XP SP2 (SP3) ¹
- System type: 32-bit and 64-bit operating systems. ¹
- Processor: Single core 1 GHz or higher
- RAM: 512 MB or higher for Windows® XP.
2 GB or higher for Windows Vista™ / Windows® 7.
- Available hard disk space: min. 500 MB before installation
- Graphics board: min. High Color (16-bit); 1024 x 768 resolution.
- Screen: 10" (25cm) or larger
- USB interfaces: Available USB port for data transfer from/to sewing computer
- Internet connection for downloading files
- Microsoft .Net Framework 4.0

Contact your dealer if the updating process fails, or if you prefer to not do the updating yourself.

Step-by-step installation instructions

- Close all programs.
- Make sure you have administrator's access to your computer.
- **DON'T connect the sewing computer yet.** (The wrong driver would be installed if the sewing computer were connected already at this point.)
- Download the 5SeriesUpdate_Vxxxxxxx² file from www.BERNINA.com/downloads and save it to C:\Temp
- If you don't have a "c:\Temp" file, create one in Windows Explorer.


Open the C:\Temp file.
Click the zipped file to unpack it.




¹ **Note:** No other operating systems but the ones mentioned above are supported.

² The letter "x" stands for a number. The numbers given refer to the firmware versions.

To start the update click file
5SeriesUpdate_Vxxxxxxx.exe




Then click




Select C:\Temp


(




Click OK to confirm




In c:\Temp doubleclick the file
5SeriesUpdate_Vxxxxxxx.msi




If this message appears, installation of
Net Framework Version 4.0 is required
before continuing.




Now select „Next“




The suggested path can be confirmed by clicking "Next"



Click "Next" to confirm




It might take a little while before the installation process is displayed



Tick "Software von BERNINA International AG immer vertrauen" (Always trust software from BERNINA International AG) and select "Installieren" (Install)



Click "Close" to finish.



Updating the sewing computer

Start the program "5 Series update"



Connect the sewing computer with the pc using the USB cable.

Press softkeys




and




and


switch the sewing computer on.



The updating process will start automatically. .



This message appears if the updating has been completed successfully.
Now restart your sewing computer.



NOTE

It might therefore happen that the sewing computer won't be recognized after installation of the new BMS. The reason is that Windows installs its own driver.

Proceed as follows to install the proper driver:

Connect the sewing computer to your PC using a USB cable.

Press key





and




switch the sewing computer on


Keeping the two keys pressed go to 5Series Driver and start it in this file:
C:\Programme(x86)\BERNINA\BERNINA 5 Series Update



Confirm with OK



Confirm with OK



The proper driver has been installed. Click the 5Series update symbol on the desktop to start the updating.

