

## Installation manual for the aurora driver (64-bit)

Below you will find step-by-step instructions to install the **aurora driver (64-bit)** on a Computer with **64-bit Windows operating system**.

### Note:

*Every computer may be assembled and configured differently, which may mean differences from the messages and figures shown here. The different configurations may affect the behaviour.*

### Urgent

**Please close all running programs before the installation.**

**The aurora sewing machine must be connected with the USB-Cable to the Computer and also switched on**

**During the installation, confirm safety warnings with "Allow".**

### 1. Download

- a. Click on the link:  [Driver \(64-Bit\) for the aurora sewing machine](#) (993KB)
- b. A window will open, click on "Run"




- c. The following Security Message may appear, confirm with "Run"




- d. After that, the process for unpacking of the data, will start


- e. Click on **“Unzip”**, without changing the path



- f. The files will be unpacked in the following path:  
**„C:\BERNINA\_Downloads\aurora\Aurora\_driver\_64bit“**
- g. The following message will be shown after successfully unzip of the files, click on **„OK“** to confirm:




- h. Close the window with **„Close“**




## 2. Installation of the driver for the aurora


- a. Open the device manager by clicking on “**Start – Control Panel – Device Manager**”.
- b. Click with the right hand side mouse key on the “Aurora 430/440” with the yellow Exclamation mark and select “**Update Driver Software**”




- c. Select in the following window:  
“**Browse my Computer for driver Software**”



- d. Click on **“Browse”**, select the following path:  
“C:\BERNINA\_downloads\aurora\Aurora\_driver\_64bit” and click on **“OK”**




- e. Click on **“Next”** for starting the installation:



The installation is running

- f. After successful installation, the following message appears, confirm with “close”




- g. The driver for the aurora is now installed.


---

### 3. *Installation of the driver for the USB-Serial port*


- a. Open the device manager by clicking on “Start – Control Panel – Device Manager”.
- b. Click with the right hand side mouse key on the “USB Serial Port” with the yellow Exclamation mark and select “Update Driver Software”




- c. Select in the following window:  
“Browse my Computer for driver Software”



- d. Click on “Browse”, select the following path:  
“C:\BERNINA\_downloads\aurora\Aurora\_driver\_64bit” and click on “OK”




e. Click on “**Next**” for starting the installation:



The installation is running


f. After successfully installation, the following message appears, confirm with “**close**”



g. The driver for the “**USB Serial Port**” is now installed.

## 4. Check the installed drivers

- a. Open the device manager by clicking on “**Start – Control Panel – Device Manager**”.



- b. Check are in the “**Device Manager**”, under “**Ports (Com & LPT)**” and “**Universal Serial Bus controllers**” the red marked entries listed.
- c. Close all open windows
- d. Connect the Dongle of your BERNINA embroidery software with a free USB-Port and start the BERNINA embroidery Software V5
- e. Open a design and send it to the aurora sewing machine with connected embroidery module.