



PLUS Upgrade for BERNINA 770 QE

Installation Instructions

Table of Contents

1	PLUS Upgrade for BERNINA 770 QE	4
1.1	Introduction	4
1.2	PLUS Upgrade overview	4
1.3	Display machine ID	4
1.4	Generate the activation key	5
1.5	Entering the activation key	5



1 PLUS Upgrade for BERNINA 770 QE

1.1 Introduction

The PLUS Upgrade for BERNINA 770 QE enhances your BERNINA 770 QE with new functions, stitch patterns and embroidery motifs.




These instructions describe the most important steps for activating the upgrade.

- Determining the machine ID
- Generating the activation key
- Activating the upgrade on your machine



You can find a full overview of all new functions at <https://www.bernina.com/B770-QE/PLUS-Upgrade>.

1.2 PLUS Upgrade overview

Illustration	Name	Purpose
	Product key card	Contains the product key for generating the activation key.
	Adjustable Ruler foot with Slit #72S	For quilting with 1/4" rulers. For free-motion quilting. For couching in combination with the Couching Inserts. For detailed information on this topic, see https://www.bernina.com/foot-72S
	Couching Inserts	To sew on wool, yarn or cords. To free-motion quilting or to quilting with rulers. For couching. For detailed information on this topic, see https://www.bernina.com/couching-inserts

1.3 Display machine ID

The machine ID is required in order to generate the activation key.



Prerequisite:

- The most up-to-date firmware version is installed on the machine. See support page <https://www.bernina.com/770qe-support>.



> Tap «Setup Pogram».



> Tap «Machine settings».



> Tap «Information».



- > Tap «Machine ID».
- The machine ID is displayed.
- If the «Machine ID» is not displayed, the most up-to-date version of the firmware must first be installed on the machine.

1.4 Generate the activation key

Prerequisite:

- The machine ID is ready.
- The product key card with product key is ready.



- > Visit the web page <https://www.bernina.com/B770-QE/PLUS-Upgrade/activation> and follow the instructions.
- After entering all the required data, the activation key is displayed and sent by email to the address you have provided.

1.5 Entering the activation key



> Tap «Setup Pogram».



> Tap «Machine settings».



> Tap «Information».



- > Tap «Upgrade».
- > Tap «Activate».
- > Enter the activation key.



- > Tap «Confirm».
- «Enabled» is displayed and the new functions in the upgrade are enabled.





BERNINA recommends threads from *Mettler*[®]

BERNINA International AG | CH-8266 Steckborn Switzerland | www.bernina.com | © Copyright by BERNINA International AG

made to create **BERNINA**

1056785.00A.04
2021-03 EN